Proce Code)	dure	Name (Procesdure	Adva	nce	Air (Carg	o Ma	anif	est	Info	rma	tio	n Re	egist	rati	on	(ADM	01)		
oN	Column	Field Name	Repeat2 Repeat1 Length Attitude		ratio	on	Condition n Correction					etio	n	Code	Input Condition/Format					
1		Input Common Field			398			М				M			M					
2		Function Type Code	SIG	an	1			_				м			М					Not in use. A space: Registration C : Correction D : Deletion of AWB preliminary information or Advance Air Cargo Manifest Information
3		Arrival Flight Number 1	FL1	an	6			М				M			м					(1) Enter "Airline Code" + "Flight Number". (2) "Flight Number" can be 3 digits or 4 digits. Only numbers are allowed for the first 3 digits of "Flight Number".
4		Arrival Flight Number 2	FL2	an	5			М				M			М					Enter the date of the flight in the following format;
5		Joint Operation Identifier	JNT	an	1			С				e			e					When the arrival flight is a joint operated flight and the implementor of this procedure isn't the operating airline company, enter "J" here.
6		Nationality Code	FLG	an	2			С				c			C				UN/LOCODE (2 digits country name)	(1) When the arrival flight is a joint operated flight, enter Nationality Code here. (2) For "Airline Code" which requires entry of Nationality Code, enter this field.
7		Estimated Date of Arrival	ADT	n	8			M C				M			М					Enter "Estimated Date of Arrival" in the following range; System date ≦ Estimated Date of Arrival
8		Estimated Time of Arrival	ATM	n	4			M	М			м			М					When "Estimated Date of Arrival" has not been entered even though "Estimated Time of Arrival" is entered, it is converted into a space and processed.
9	10	Air Waybill Number	AWB	an	20			М				M			М					(1) For Air Waybill, 11 digits at most can be entered. (2) For ULD, 14 digits at most can be entered. (3) Air Waybill Number whose first 3 digits are "XXX" will be excluded from the target of processing.
10	*	Split Identifier	SPT	an	1				С				С		=					(1) For split cargo, enter "S". (2) When the cargo already has been registered as split cargo, entry of this field can be omittted. (3) For ULD, entry is NOT allowed.
11	*	ULD Identifier	ULD	an	1				С				c		-					(1) When the cargo is loaded in ULD, enter "U". (2) For ULD, enter "K".
12	*	Arrival Number of Pieces	PCS	n	6				С				c		-					(1) For ULD, entry is not allowed. (2) When it is not ULD, entry is mandatory.
13	*	Arrival Weight	WGT	n	8				С				c		=					(1) Integral part is 6 digits at most and decimal part is 1 digit at most. (2) For ULD, entry is not allowed.
14	*	Weight Unit Code	JTI	an	3					G F				c	=				Codes for Units of Measurement (UN/ECE Recommendations	When entry of this field is omitted, Weight Unit Code for the previous column will be copied to this field. KGM: Kilogram LBR: Pound
15	*	Goods Description	CMD	an	21				M				M		1					(1) For ULD, enter the number of AWB loaded in ULD. (2) Enter concrete and detailed information which is sufficient for specifying loaded cargo. (3) Entry of vague information is NOT allowed.
16	*	Special Cargo Code	SPC	an	3				С				е		-				SPC Code	For ULD, entry is not allowed.
17	*	Place of Origin Code	ORG	an	3				С				e		-				IATA Airport Code and IATA City Code	(1) When Place of Origin Code is not registered in NACCS, enter "ZZZ". (2) When the entry of this field is omitted, Place of Origin Code for the previous column will be copied to this field.
18	*	Place of Destination Code	DST	an	3				С				G		_				IATA Airport Code and IATA City Code	(1) For "Temporary Landing Cargo", "Temporary Landing Cargo which will be transferred to other Japanese airport for temporary landing", "Blanket Bonded Transportation Temporary Landing Cargo for other Japanese airport" or "Cargo transferred to foreign outbound aircraft"; enter "foreign city code" or "Japanese airport code which is not registered in NACCS". (2) For "Temporary Landing Cargo which will be transferred to other Japanese airport to be imported" or "Cargo transferred to domestic aircraft"; enter "domestic airport code" registered in NACCS. (3) For "Blanket Bonded Transportation Cargo for other Japanese airport", enter airport code which satisfies both of the following conditions: - The airport code stands for an airport other than arrival airport. - The airport code stands for an airport to which blanket bonded transportation is possible. (4) In the cases other than above: "arrival airport code" should be entered. (5) When the entry of this field is omitted, Place of Destination Code for the previous column will be copied to this field.

Proced Code)	dure	Name (Procesdure	Adva	nce	Air (Carg	o Ma	nifes	t I	nform	natio	on R	Regi	stra	tio	n (ADI	MO1)		
00007				~	1	Ι												1	
No	Column	Field Name	ID	Attitude	Length	Repeat1	Repeat2	Regia	gistration			Correction				eletio	on	Code	Input Condition/Format
19	*	Transportation Type	USB	an	1			c	;			Ф			=				(1) For "Cargo unloaded at arrival airport" or "Temporary Landing Cargo": do not enter this field. (2) For "Temporary Landing Cargo which will be transferred to other Japanese airport to be imported" or "Temporary Landing Cargo which will be transferred to other Japanese airport for temporary landing": enter "K". (3) For "Blanket Bonded Transportation Cargo for other Japanese airport": enter "T". (4) For "Airline Belongings which will be transferred to airline bonded warehouse": enter "1". (5) For "Blanket Bonded Transportation Temporary Landing Cargo for other Japanese airport": enter "H". (6) For "Cargo which will be transferred to other aircraft": enter "M". (7) When Transportation Type is not determined, enter "?"". (8) When Place of Destination Code and Transportation Type is not entered, Transport Type will be entered from above Column.
20	*	Check Digit Unnecessity Identifier	CDT	an	1			C	;			c			_				(1) When check digit is unnecessary, enter "N". (2) For ULD, entry is not allowed.
21		Airline Belongings Identifier	SV0	an	1			C	; _			G			-				(1) For Airline Belongings, enter "S". (2) For ULD, entry is not allowed.
22	*	Total Number of Pieces	GPS	n	6			C	;			С			-				(1) Enter Total Number of pieces, in case of Split Cargo. (2) Arrival Number of Pieces < Total Number of Pieces (3) For ULD, entry is not allowed. (4) When Total Number of Pieces has already been registered in Import Cargo Information DB in NACCS, entry of this field can be omitted. However, when this field is entered, the entered data will be used rather than registered data in DB.
23	*	Total Weight	GWT	n	8			C	;			e			-				(1) Enter Total Number of pieces, in case of Split Cargo. (2) Arrival Weight < Total Weight (3) For ULD, entry is not allowed. (4) When Total Weight has already been registered in Import Cargo Information DB in NACCS, entry of this filed can be omitted. However, when this field is entered, the entered data will be used rather than registered data in DB. (5) (3) Integral part is 6 digits at most and decimal part is 1 digit at most.
24	*	Weight Unit Code	GTI	an	3				G F				C		=			Codes for Units of Measurement (UN/ECE Recommendations 20m alphabetic Code)	(1) For ULD, entry is not allowed. (2) When entry of this field is omitted, Weight Unit Code for the previous column will be copied to this field. KGM: Kilogram LBR: Pound
25	*	Consignor Name	SHN	an	70			C	;			e			-				When it is not ULD, entry is mandatory.
26	*	Consignor Address	SHA	an	105			C	;			c			-				When it is not ULD, entry is mandatory.
27		Consignor Telephone Number	STL	an	14			C	;			c			-				
28	*	Consignee Code	CNC	an	17			C	;			c			=			Exporter/Importer Code Corporate Number	
29	*	Consignee Name	CNN	an	70			C	;			c			-				When it is not ULD, entry is mandatory.
30	*	Consignee Address	CNA	an	105			C	;			c			=				When it is not ULD, entry is mandatory
31		Consignee Telephone Number	CTL	an	14			C	;			c			=				