

Appendix 8 Table of Input Fields of Advance Cargo Information Registration (AMR)

Field No. (* 1)	Field Name	Category (* 2)		Operation Code (* 3)	Particulars
2	Function Type Code	M			Enter "9."
3	SP Code	C			No entry is required. * Those who run service provider business operations send a Service Provider Code and password to NACCS.
4	Vessel Code	M		Distinctive letter (call sign)	(1) Enter the vessel's distinctive letter (call sign). (2) Enter it in the left-aligned format.
5	Laden Vessel Name	F			(1) If the Vessel Code entered in "Item No. 4" is registered in NACCS, no entry is required. (2) If the Vessel Code entered in "Item No. 4" is not registered in NACCS, a Vessel Name must be entered.
6	Nationality Code of Vessel	F		Country Code (Refer to UN/LOCODE in Operation Codes (including the Country Code.))	(1) If the Vessel Code entered in "Field No. 4" is registered in NACCS, no entry is required. (2) If the Vessel Code entered in "Field No. 4" is not registered in NACCS, a Country Code (2-digit Country Code of UN/LOCODE. Hereinafter the same.) must be entered for the vessel nationality.
7	Voyage Number	M			Enter the Voyage Number.
8	Carrier Code	M			Enter the Carrier Code for NACCS (*) in units of the carrier using the ship. * The code is given by the NACCS Center to a shipping company.
9	Port of Loading Code	M		Port Code (Refer to UN/LOCODE in Operation Codes (including the Country Code.))	(1) For a port where container cargo is loaded onto a vessel intended for entry into a port in Japan, enter the Port Code (UN/LOCODE 5 digits). In case of transshipment, enter the port where cargo is firstly shipped for Japan (port of origin) in "Field No. 23." (2) If the Port Code (UN/LOCODE 5 digits) is not registered in NACCS, enter a code with "ZZZ" after the Country Code (2 digits).
10	Name of Port of Loading	F			(1) If the port of loading code entered in "Field No. 9" is registered in NACCS, no entry is required. (2) If the lower 3 digits of Port of Loading Code entered in "Field No. 9" are "ZZZ," the Port of Loading Name must be entered.
11	Port of Loading Suffix	C			(1) If a vessel makes more than one port call in a single voyage, enter the Branch Number. (2) If the port call at the same port is the second one in the same voyage, enter "1," and if the third one, "2." Subsequently, up to "9" can be entered. Meanwhile, be careful not to enter a Branch Number which does not match the number of port calls.
12	B/L number	M			(1) Follow the entry method below and enter the B/L number. (2) Enter "." (period) for "," (comma). (Entry Method) 1) 1st through 4th digits Enter the Carrier Code for NACCS. If the Carrier Code for NACCS is 3 digits, enter "-" (hyphen) in the 4th digit. 2) 5th through 16th digits Enter the Ocean (Master) B/L number within 12 digits. 3) 17th through 20th digits

Field No. (* 1)	Field Name	Category (* 2)		Operation Code (* 3)	Particulars																																												
					Enter the Branch Number within 4 digits after 2 above as required. When entering the Branch Number, follow the following instructions: If one B/L number has more than 100 containers, follow the order in the table below, and divide the containers by adding the Branch Number after the B/L number in the left-aligned format so that the number of containers can be 100 or less. In addition, after the Branch Number is added, users using NACCS to perform subsequent operations for the B/L number should be notified of the addition of the Branch Number to the B/L number and the particulars of the division. <table><tr><th>Order</th><th>Branch Number</th><th>Order</th><th>Branch Number</th></tr><tr><td>1</td><td>W</td><td>11</td><td>XY</td></tr><tr><td>2</td><td>X</td><td>12</td><td>XZ</td></tr><tr><td>3</td><td>Y</td><td>13</td><td>YW</td></tr><tr><td>4</td><td>Z</td><td>14</td><td>YX</td></tr><tr><td>5</td><td>WW</td><td>15</td><td>YY</td></tr><tr><td>6</td><td>WX</td><td>16</td><td>YZ</td></tr><tr><td>7</td><td>WY</td><td>17</td><td>ZW</td></tr><tr><td>8</td><td>WZ</td><td>18</td><td>ZX</td></tr><tr><td>9</td><td>XW</td><td>19</td><td>ZY</td></tr><tr><td>10</td><td>XX</td><td>20</td><td>ZZ</td></tr></table> (Entry Example) (1) If the Carrier Code for NACCS is “NACS” and the Ocean (Master) B/L number is 123456789012:” B/L number <u>NACS123456789012</u> (2) If the Carrier Code for NACCS is “NACS,” The Ocean (Master) B/L number is “123456789012” and the number of containers is 200: a. 1-100 B/L number <u>NACS123456789012W</u> b. 101-200 B/L number <u>NACS123456789012X</u>	Order	Branch Number	Order	Branch Number	1	W	11	XY	2	X	12	XZ	3	Y	13	YW	4	Z	14	YX	5	WW	15	YY	6	WX	16	YZ	7	WY	17	ZW	8	WZ	18	ZX	9	XW	19	ZY	10	XX	20	ZZ
Order	Branch Number	Order	Branch Number																																														
1	W	11	XY																																														
2	X	12	XZ																																														
3	Y	13	YW																																														
4	Z	14	YX																																														
5	WW	15	YY																																														
6	WX	16	YZ																																														
7	WY	17	ZW																																														
8	WZ	18	ZX																																														
9	XW	19	ZY																																														
10	XX	20	ZZ																																														
13	Estimated Date of Departure	M			Enter the western calendar format (8 digits) for the Scheduled Date of Departure from the cargo loading port at local time or Greenwich mean time (GMT).																																												
14	Estimated Time of Departure (from the port of loading)	M			Enter the time (4 digits) of the Estimated Time of Departure from the cargo loading port at local time or Greenwich mean time (GMT).																																												
15	Time Difference from Greenwich Mean Time	M			(1) If the Estimated Date of Departure in “Field No. 13” and “Estimated Time of Departure” (from the port of loading) in “Field No. 14” are entered at local time, enter the time difference between the local time and Greenwich mean time (GMT) in hour(s) and minute (s) (4 digits) with a plus or minus sign “+” or “-.” (Entry Example) 1) If the cargo loading port is “USLAX”																																												

Field No. (* 1)	Field Name	Category (* 2)		Operation Code (* 3)	Particulars
					Local time: 18:02 on January 10 GMT: 02:02 on January 11 GMT Subtraction +0800 2) If the cargo loading port is "CNTAO" Local time: 10:02 on January 11 GMT: 02:02 on January 11 GMT Subtraction -0800 3) If the cargo loading port is "MMRGN" Local time: 08:32 on January 11 GMT: 02:02 on January 11 GMT Subtraction -0630 (2) The Estimated Date of Departure in "Field No. 13" and Estimated Time of Departure (from the port of loading) in "Field No. 14" are entered in GMT, enter "00000."
16	Relaxed Application Area Identifier	C			In case of departure from a port in an area where the application for the filing deadline is relaxed (*), enter "Y." * Refer to the main document 3-(3)-B and Appendix 2.
17	Master B/L Identifier	C			If a related House B/L exists for the B/L number in "Field No. 12," enter "M."
* [18] fields can be repeatedly entered up to three times.					
18	Notification Forwarding Party Code	C		User Code (*) * The code is provided by the NACCS Center in entering into an agreement for use to identify a user. Note that it differs from the Reporter ID in 4-(3) of the main document. (Hereinafter the same shall apply in this document.)	If Japan Customs needs to send an advance notice of risk analysis results to other users, use the user code of the user.
19	Port of Discharge Code	M		Port Code (Refer to UN/LOCODE in Operation Codes (including the Country Code.))	(1) Enter the Port Code (UN/LOCODE 5 digits) for a port where container cargo is unloaded (in case of a temporary landing, a port where cargo is temporary landing). (2) If the Port Code (UN/LOCODE 5 digits) is not registered in NACCS, enter a code with "ZZZ" after the Country Code (2 digits).
20	Port of Discharge Suffix	C			(1) If a vessel makes more than one port call in a single voyage, enter the Branch Number. (2) If the port call at the same port is the second one in the same voyage, enter "1," and if the third one, "2." Subsequently, up to "9" can be entered. Meanwhile, be careful not to enter a Branch Number which does not match the number of port calls.
21	Estimated Date of Arrival (at the port of discharge)	M			(1) Enter the Estimated Date of Arrival (at the port of discharge) in the western calendar format (8 digits) (2) Enter the time in Japanese Standard Time (JST).
22	Container Operator Code	C		User Code	(1) If cargo is carried in a container yard after it is unloaded in Japan, enter the user code of a

Field No. (* 1)	Field Name	Category (* 2)		Operation Code (* 3)	Particulars
					container operation company. (2) If the container operation company does not obtain any user code, enter "99999." (3) Manifest Information Registration (Blanket Registration) (MFI) is used in subsequent operations of NACCS and must be entered.
23	Port of Origin code	M		Port Code (Refer to UN/LOCODE in Operation Codes (including the Country Code.))	(1) Enter the Port Code (UN/LOCODE 5 digits) for the Port of Origin of container cargo. In case of transshipment, enter the port where cargo is firstly shipped for Japan (port of origin). (2) If the Port Code (UN/LOCODE 5 digits) is not registered in NACCS, enter a code with "ZZZ" after the Country Code (2 digits).
24	Port of Origin Name	F			(1) If the Port of Origin Code entered in "Field No. 23" is registered in NACCS, no entry is required. (2) If "ZZZ" is entered in the lower 3 digits of the Port Code entered in "Field No. 23," the Port of Origin Name must be entered.
25	Place of Delivery Code	M		City Code (Refer to UN/LOCODE in Operation Codes (including the Country Code.))	(1) Enter the City Code (UN/LOCODE 5 digits) for the Place of Delivery of the container cargo. In the case of temporary landing cargo, it is not the same as the port of loading code entered in "Field No. 19" (2) If the City Code is not registered in NACCS, enter the code with "ZZZ" after the Country Code (2 digits).
26	Place of Delivery Name	F			(1) If the delivery venue entered in "Field No. 25" is registered in NACCS, no entry is required. (2) If "ZZZ" is entered in the lower 3 digits of the Place of Delivery Code entered in "Field No. 25," the delivery venue must be entered.
27	Final Destination Code	C		City Code (Refer to UN/LOCODE in Operation Codes (including the Country Code.))	(1) Enter the City Code (UN/LOCODE 5 digits) for the final destination of container cargo. (2) If the City Code is not registered in NACCS, enter the code with "ZZZ" after the Country Code (2 digits).
28	Final Destination Name		F		(1) If the Final Destination Name entered in "Field No. 27" is registered in NACCS, no entry is required. (2) If "ZZZ" is entered in the lower 3 digits of the final destination code entered in "Field No. 27," the Final Destination Name must be entered.
29	Consignor Code	C		Importer Exporter Code (*) * The code provided by Japan Customs or the Japan Association for Simplification of International Trade Procedures (JASTPRO) to identify importers/exporters.	(1) In case of a consignor with an Importer Exporter Code, enter the Importer Exporter Code. (2) In case of a consignor without any Importer Exporter Code, no entry is required.
30	Consignor Name	F			(1) If a Consignor Code is entered in "Field No. 29," no entry is required. (2) If no Consignor Code is entered in "Field No. 29," a Consignor Name must be entered.
31	Consignor Address (block entry)	C			(1) If a Consignor Code is entered in "Field No. 29," no entry is available. (2) Entry is unavailable if Consignor Address 1/4

Field No. (* 1)	Field Name	Category (* 2)		Operation Code (* 3)	Particulars
					(Street and number/P.O. box) through Consignor Address 3/4 (city name) are entered.
32	Consignor Address 1/4 (Street and number/P.O. box)	C			(1) If a Consignor Code is entered in "Field No. 29," no entry is required. (2) If no Consignor Code is entered in "Field No. 29," enter the Consignor Address 1/4 (Street and number/P.O. box).
33	Consignor Address 2/4 (Street and number/P.O. box)	C			(1) If a Consignor Code is entered in "Field No. 29," no entry is required. (2) If no Consignor Code is entered in "Field No. 29," enter the Consignor Address 2/4 (Street and number/P.O. box).
34	Consignor Address 3/4 (Country sub-entry, name)	C			(1) If a Consignor Code is entered in "Field No. 29," no entry is required. (2) If no Consignor Code is entered in "Field No. 29," enter the Consignor Address 3/4 (City name)
35	Consignor Address 4/4 (City name)	C			(1) If a Consignor Code is entered in "Field No. 29," no entry is required. (2) If no Consignor Code is entered in "Field No. 29," enter the Consignor Address 4/4 (Country sub-entity, name).
36	Consignor Postal Code (Postcode identification)	C			(1) If a Consignor Code is entered in "Field No. 29," no entry is required. (2) If no Consignor Code is entered in "Field No. 29," enter Consignor Postcode (Postcode identification). (Do not enter any delimiter.) (3) If there is no postcode in the country of consignor, no entry is required.
37	Consignor Country Code (Country, coded)	F		Country Code (Refer to UN/LOCODE in Operation Codes (including the Country Code.))	(1) If a Consignor Code is entered in "Field No. 29," no entry is required. (2) If no Consignor Code is entered in "Field No. 29," a country code (2 digits) must be entered.
38	Consignor Telephone Number	C			(1) If a Consignor Code is entered in "Field No. 29," no entry is required. (2) If no Consignor Code is entered in "Field No. 29," enter a telephone number from a long distance code. (Do not enter any delimiter.)
39	Consignee Code	C		Importer Exporter Code	(1) In case of the consignee with an Importer Exporter Code, enter the Importer Exporter Code. (2) In case of the consignee without any Importer Exporter Code, no entry is required.
40	Consignee Name	F			(1) If a Consignee Code is entered in "Field No. 39," no entry is required. (2) If no Consignee Code is entered in "Field No. 39," a Consignee Name must be entered.
41	Consignee Address (block entry)	C			(1) If a Consignee Code is entered in "Field No. 39," no entry is available. (2) Entry is unavailable if the Consignee Address 1/4 (Street and number/P.O. box) "Field No. 42" through Consignee Address 3/4 (City name) in "Field No. 44" are entered.
42	Consignee Address 1/4 (Street and number/P.O. box)	C			(1) If a Consignee Code is entered in "Field No. 39," no entry is required. (2) If no Consignee Code is entered in "Field No. 39," enter the Consignee Address 1/4 (Street and number/P.O. box).
43	Consignee	C			(1) If a Consignee Code is entered in "Field No.

Field No. (* 1)	Field Name	Category (* 2)		Operation Code (* 3)	Particulars
	Address 2/4 (Street and number/P.O. box)				39," no entry is required. (2) If no Consignee Code is entered in "Field No. 39," enter the Consignee Address 2/4 (Street and number/P.O. box).
44	Consignee Address 3/4 (City name)	C			(1) If a Consignee Code is entered in "Field No. 39," no entry is required. (2) If no Consignee Code is entered in "Field No. 39," enter the Consignee Address 3/4 (City name)
45	Consignee Address 4/4 (Country sub-entity, name)	C			(1) If a Consignee Code is entered in "Field No. 39," no entry is required. (2) If no Consignee Code is entered in "Field No. 39," enter the Consignee Address 4/4 (Country sub-entity, name).
46	Consignee Postal Code (Postcode identification)	C			(1) If a Consignee Code is entered in "Field No. 39," no entry is required. (2) If no Consignee Code is entered in "Field No. 39," enter Consignee Postcode (Postcode identification). (Do not enter any delimiter.)
47	Consignee Country Code (Country, coded)	F		Country Code (Refer to UN/LOCODE in Operation Codes (including the Country Code.))	(1) If a Consignee Code is entered in "Field No. 39," no entry is required. (2) If no Consignee Code is entered in "Field No. 39," a country code (2 digits) must be entered for the country name of the consignee
48	Consignee Telephone Number	C			(1) If a Consignee Code is entered in "Field No. 39," no entry is required. (2) If no Consignee Code is entered in "Field No. 39," enter a telephone number from a long distance code. (Do not enter any delimiter.)
* Fields [49] through [58] can be repeatedly entered up to twice.					
49	Notify Party Code	C		Importer Exporter Code	(1) In case of a notify party with an Importer Exporter Code, enter the Importer Exporter Code. (2) In case of a notify party without any Importer Exporter Code, no entry is required.
50	Notify Party Name	C			(1) If a Notify Party Code is entered in "Field No. 49," no entry is required. (2) If a no Notify Party Code is entered in "Field No. 49," Notify Party Name must be entered.
51	Notify Party Address (block entry)	C			(1) If a Notify Party Code is entered in "Field No. 49," no entry is required. (2) When entering a notify party address 1/4 (Street and number/P.O. box) in "Field No. 52" through Notify Party Address3/4 (City name) in "Field No. 54," entry is unavailable.
52	Notify Party Address1/4 (Street and number/P.O. box)	C			(1) If a Notify Party Code is entered in "Field No. 49," no entry is required. (2) If no Notify Party Code is entered in "Field No. 49," enter the Notify Party Address 1/4 (Street and number/P.O. box).
53	Notify Party Address2/4 (Street and number/P.O. box)	C			(1) If a Notify Party Code is entered in "Field No. 49," no entry is required. (2) If no Notify Party Code is entered in "Field No. 49," enter the Notify Party Address 2/4 (Street and number/P.O. box).
54	Notify Party Address 3/4 (City name)	C			(1) If a Notify Party Code is entered in "Field No. 49," no entry is required. (2) If no Notify Party Code is entered in "Field No. 49," enter the Notify Party Address 3/4 (City name)

Field No. (* 1)	Field Name	Category (* 2)		Operation Code (* 3)	Particulars
55	Consignee Address 4/4 (Country sub-entity, name)	C			(1) If a Notify Party Code is entered in "Field No. 49," no entry is required. (2) If no Notify Party Code is entered in "Field No. 49," enter the Notify Party Address 4/4 (Country sub-entity, name)
56	Notify Party Postal Code (Postcode identification)	C			(1) If a Notify Party Code is entered in "Field No. 49," no entry is required. (2) If no Notify Party Code is entered in "Field No. 49," enter the Notify Party Postcode (Postcode identification). (Do not enter any delimiter.)
57	Notify Party Country Code (Country, coded)	C		Country Code (Refer to UN/LOCODE in Operation Codes (including the Country Code.))	(1) If a Notify Party Code is entered in "Field No. 49," no entry is required. (2) If no Notify Party Code is entered in "Field No. 49," a country name (2 digits) of the notify party must be entered.
58	Notify Party Telephone Number	C			(1) If a Notify Party Code is entered in "Field No. 49," no entry is required. (2) If no Notify Party Code is entered in "Field No. 49," enter a telephone number from a long distance code. (Do not enter any delimiter.)
59	Goods Description	M			(1) Enter specific and detailed description of goods so that cargo particulars can be easily identified. (2) Only numbers and marks cannot be entered.
60	Harmonized System Code	M		Harmonized System Code (HS code) (6-digit)	Enter representative goods in HS code (6 digits).
61	Mark and Number	M			Enter the Mark and Number of Cargo.
62	Number of Packages	M			(1) Enter the number of outer packages (2) "Zero (0)" cannot be entered. If packages cannot be counted, enter "1."
63	Number of Packages Unit Code	M		Codes for Types of Packages (Refer to Operation Codes)	Enter the Package Type Code as the number of packages unit code.
64	Gross Weight	M			(1) Enter the Total Gross Weight of cargo. (2) "Zero (0)" cannot be entered. (3) Entries can be made up to the third decimal place. (4) If an integer portion is 7 digits, the weight unit code should be "KGM." (5) If Total Gross Weight is not the weight unit code in "Field No. 65," enter a weight converted into the unit.
65	Weight Unit Code	M		Codes for Units of Measurement (Total Gross Weight and Total Volume) (Refer to Operation Codes)	Enter the weight unit in Codes for Units of Measurement (Total Gross Weight and Total Volume).
66	Net Weight	C			(1) Enter the Net Weight of the cargo. (2) "Zero (0)" cannot be entered. (3) Entries can be made up to the third decimal place. (4) If an integer portion is 7 digits, the weight unit code in "Field 67" should be "KGM." (5) If the Net Weight is not the weight unit code in "Field No. 67," enter a weight converted into the unit.

Field No. (* 1)	Field Name	Category (* 2)		Operation Code (* 3)	Particulars
67	Weight Unit Code		M	Codes for Units of Measurement (Total Gross Weight and Total Volume) (Refer to Operation Codes)	Enter the unit of Net Weight in Codes for Units of Measurement (Total Gross Weight and Total Volume).
68	Measurement	M			(1) Enter a cargo volume. (2) "Zero (0)" cannot be entered. (3) Entries can be made up to the third decimal place. (4) If the volume is not the volume code in "Field No. 69," enter a volume converted into the unit.
69	Measurement Unit Code	M		Codes for Units of Measurement (Total Gross Weight and Total Volume) (Refer to Operation Codes)	Enter the volume unit in Codes for Units of Measurement (Total Gross Weight and Total Volume).
70	Country of Origin Code	C		Country Code (Refer to UN/LOCODE in Operation Codes (including the Country Code.))	Enter the Country Code (2 digits) for the country of origin of the cargo.
71	Dangerous Cargo Code	C		Dangerous Cargo Code (Refer to SPC (special cargo) of Operation Codes/ Hazard Code)	If a special cargo is loaded, enter Special Cargo Code for the type of special cargo.
72	IMDG Class	C			If a dangerous cargo is loaded, enter a hazard category (class) in the International Maritime Dangerous Goods Code (IMDG code).
73	UN No.		M		(1) Enter the UN No. pursuant to United Nations Recommendations on the Transport of Dangerous Goods. (2) Enter a number from "0000" to "9999."
74	Freight	C			(1) Enter cargo freight. (2) When entering a Freight Currency Code other than "JPY" in "Field No. 75," entries can be made up to the second decimal place.
75	Freight Currency Code		M	Currency Code (Refer to Operation Codes)	Enter the Currency Code to show a currency type of freight.
76	Value	C			(1) If customs transit takes place after a temporary landing in Japan, enter the cargo values. (2) When entering a value currency code other than "JPY" in "Field No. 77," entries can be made up to the second decimal place.
77	Value Currency Code		M	Currency Code (Refer to Operation Codes)	Enter the Currency Code for a currency type of value.
78	General Customs Transit Approval Number	C			If individual customs transit associated with a general customs transit approval is conducted after unloading in Japan, enter a general customs transit approval number.
79	Temporary Landing Identifier	C			Enter "28" in case of temporary landing cargo.
80	Reason for Temporary Landing Code		M	Reason for Temporary Landing Code (Refer to Operation	(1) In case of temporary landing cargo, enter a temporary landing cause code. (2) The registration of customs transit information

Field No. (* 1)	Field Name	Category (* 2)		Operation Code (* 3)	Particulars														
				Codes)	for temporary landing cargo is not "POS" (freight operations in a ship).														
81	Duration of Temporary Landing		M		(1) In case of temporary landing cargo, enter the length of the temporary landing period in days, using the discharge start time and date as the initial date of reckoning. (2) "Zero (0)" cannot be entered.														
82	Estimated Start Date of Transportation		C		(1) In case of customs transit of temporary landing cargo, enter the western calendar format (8 digits) for the start date of the transportation period. (2) Enter the time in Japanese Standard Time (JST).														
83	Estimated Finish Date of Transportation		C		(1) In case of customs transit of temporary landing cargo, enter the western calendar format (8 digits) for the end date of the transportation period. (2) Enter the time in Japanese Standard Time (JST).														
84	Code of Transportation Mode of Separate Transit/Customs Transit of Temporary Landing Cargo	C			(1) In conducting customs transit of temporary landing cargo, enter codes according to the following categories: (2) In conducting individual customs transit associated with a comprehensive customs transit approval, enter codes according to the following categories: <table border="1" style="margin-top: 10px;"> <thead> <tr> <th>Category</th> <th>Code</th> </tr> </thead> <tbody> <tr> <td>AIRCRAFT</td> <td>6</td> </tr> <tr> <td>SHIP</td> <td>11</td> </tr> <tr> <td>BARGE</td> <td>16</td> </tr> <tr> <td>RAIL EXPRESS</td> <td>25</td> </tr> <tr> <td>TRUCK</td> <td>31</td> </tr> <tr> <td>OTHER</td> <td>17</td> </tr> </tbody> </table>	Category	Code	AIRCRAFT	6	SHIP	11	BARGE	16	RAIL EXPRESS	25	TRUCK	31	OTHER	17
Category	Code																		
AIRCRAFT	6																		
SHIP	11																		
BARGE	16																		
RAIL EXPRESS	25																		
TRUCK	31																		
OTHER	17																		
85	Arrival Place Code	C		Bonded Area Code (Refer to Operation Codes)	In conducting the individual customs transit associated with a comprehensive customs transit approval or customs transit of temporary landing cargo, enter the Bond Area Code for a destination.														
86	Arrival Place Name	C			(1) If Destination Code is entered in "Field No. 85," no entry is available. (2) If Destination Code in "Field No. 85" is not entered or an entered destination code is not registered in NACCS, the Destination Name must be entered.														
* [87] field can be repeatedly entered up to five times.																			
87	Code of Other Relevant Laws and Ordinances	C		Code of Other Relevant Laws and Ordinances (Refer to Operation Codes)	In conducting individual customs transit associated with comprehensive customs transit approval or customs transit of temporary landing cargo and laws other than Customs-related are applied to cargo, enter the code associated with the law.														
88	Remark	C			Enter cargo information as required.														
89	Reference Number for Internal Use	C			Enter any number, etc. provided by your own company.														
* Fields [90] through [99] can be repeatedly entered up to 100th times.																			
90	Container Number	M			Enter the Container Number in the left-aligned format.														
* [91] Field can be repeatedly entered up to six times.																			
91	Seal Number		M		(1) Enter Seal Number of container in the left-aligned format. (2) If there is no seal, enter "NO SEAL" in the 1st														

Field No. (* 1)	Field Name	Category (* 2)		Operation Code (* 3)	Particulars																										
					field.																										
92	Empty/Full Container Identification		M		Enter “5” (full).																										
93	Container Size Code		M		Enter the Container Size Code for the container size. 1st digit: Container length code(code: length [ft])<table><tr><th>Category</th><th>Code</th></tr><tr><td>10'</td><td>1</td></tr><tr><td>20'</td><td>2</td></tr><tr><td>40'</td><td>4</td></tr><tr><td>Others length.</td><td>9</td></tr></table> 2nd digit: Container height code(code: height [ft]"[inch]"")<table><tr><th>Category</th><th>Code</th></tr><tr><td>8'</td><td>0</td></tr><tr><td>8'6"</td><td>2</td></tr><tr><td>9'</td><td>4</td></tr><tr><td>9'6"</td><td>5</td></tr><tr><td>> 9'6"</td><td>6</td></tr><tr><td>4'3"</td><td>8</td></tr><tr><td>≤ 4' (use this code for other heights.)</td><td>9</td></tr></table>	Category	Code	10'	1	20'	2	40'	4	Others length.	9	Category	Code	8'	0	8'6"	2	9'	4	9'6"	5	> 9'6"	6	4'3"	8	≤ 4' (use this code for other heights.)	9
Category	Code																														
10'	1																														
20'	2																														
40'	4																														
Others length.	9																														
Category	Code																														
8'	0																														
8'6"	2																														
9'	4																														
9'6"	5																														
> 9'6"	6																														
4'3"	8																														
≤ 4' (use this code for other heights.)	9																														
94	Container Type Code		M		Enter the Container Type Code for the container format (type).<table><tr><th>Category</th><th>Code</th></tr><tr><td>Dry container</td><td>GP</td></tr><tr><td>Reefer container</td><td>RT</td></tr><tr><td>Open top container</td><td>UT</td></tr><tr><td>Flat rack container</td><td>PF</td></tr><tr><td>Platform container</td><td>PL</td></tr><tr><td>Tank container</td><td>TN</td></tr><tr><td>Others</td><td>SN</td></tr></table>	Category	Code	Dry container	GP	Reefer container	RT	Open top container	UT	Flat rack container	PF	Platform container	PL	Tank container	TN	Others	SN										
Category	Code																														
Dry container	GP																														
Reefer container	RT																														
Open top container	UT																														
Flat rack container	PF																														
Platform container	PL																														
Tank container	TN																														
Others	SN																														
95	Service Type on Delivery Code		C		(1) Enter the delivery code according to the following categories: (2) In using MFI in subsequent operations, it must be entered.<table><tr><th>Category</th><th>Code</th></tr><tr><td>Delivery in CY</td><td>51</td></tr><tr><td>Delivery in CFS</td><td>52</td></tr><tr><td>Delivery at the door (of consignees)</td><td>53</td></tr></table>	Category	Code	Delivery in CY	51	Delivery in CFS	52	Delivery at the door (of consignees)	53																		
Category	Code																														
Delivery in CY	51																														
Delivery in CFS	52																														
Delivery at the door (of consignees)	53																														
96	Container Ownership Code		M		Enter codes for container ownership according to the following categories:<table><tr><th>Category</th><th>Code</th></tr><tr><td>Shipper supplied</td><td>1</td></tr><tr><td>Carrier supplied</td><td>2</td></tr><tr><td>Consolidator supplied</td><td>3</td></tr><tr><td>Deconsolidator supplied</td><td>4</td></tr><tr><td>Third party supplied</td><td>5</td></tr></table>	Category	Code	Shipper supplied	1	Carrier supplied	2	Consolidator supplied	3	Deconsolidator supplied	4	Third party supplied	5														
Category	Code																														
Shipper supplied	1																														
Carrier supplied	2																														
Consolidator supplied	3																														
Deconsolidator supplied	4																														
Third party supplied	5																														
97	Vanning Type Code		C		(1) Enter vanning codes according to the following categories: (2) In using MFI in subsequent operations, it must be entered.<table><tr><th>Category</th><th>Code</th></tr><tr><td>Carrier loads</td><td>1</td></tr><tr><td>Shipper loads</td><td>4</td></tr><tr><td>Consignee loads</td><td>16</td></tr></table>	Category	Code	Carrier loads	1	Shipper loads	4	Consignee loads	16																		
Category	Code																														
Carrier loads	1																														
Shipper loads	4																														
Consignee loads	16																														
98	Customs		C		(1) Enter codes according to the following																										

Field No. (* 1)	Field Name	Category (* 2)		Operation Code (* 3)	Particulars								
	Convention on Containers (CCC) Application Identifier				categories. (2) In using MFI in subsequent operations, it must be entered. <table><tr><th>Category</th><th>Code</th></tr><tr><td>If Article 8 (Special Act for International Containers, etc.) of the Act on Special Provisions of the Customs Law, etc. Incidental to customs conventions on containers and the Convention on International Transport of Goods Under Cover of TIR Carnets (TIR Convention) (hereinafter called “Special Act for Container Conventions”) is not applied to containers covered by container conventions</td><td>1</td></tr><tr><td>If Article 8 (Special Act for International Containers, etc.) of Special Act for Container Conventions is applied to containers covered by container conventions</td><td>2</td></tr><tr><td>In case containers are not covered by container conventions</td><td>3</td></tr></table>	Category	Code	If Article 8 (Special Act for International Containers, etc.) of the Act on Special Provisions of the Customs Law, etc. Incidental to customs conventions on containers and the Convention on International Transport of Goods Under Cover of TIR Carnets (TIR Convention) (hereinafter called “Special Act for Container Conventions”) is not applied to containers covered by container conventions	1	If Article 8 (Special Act for International Containers, etc.) of Special Act for Container Conventions is applied to containers covered by container conventions	2	In case containers are not covered by container conventions	3
Category	Code												
If Article 8 (Special Act for International Containers, etc.) of the Act on Special Provisions of the Customs Law, etc. Incidental to customs conventions on containers and the Convention on International Transport of Goods Under Cover of TIR Carnets (TIR Convention) (hereinafter called “Special Act for Container Conventions”) is not applied to containers covered by container conventions	1												
If Article 8 (Special Act for International Containers, etc.) of Special Act for Container Conventions is applied to containers covered by container conventions	2												
In case containers are not covered by container conventions	3												
99	Automatic Search for Discharged Container Exclusion Identifier		C		If a discharged container list is not submitted through NACCS, enter “A.”								

(* 1) Field numbers of Operation Specifications (input fields) for operations.

Operation Specifications are in the Advance Filing Rules web site (<http://www.naccscenter.com/afr/>).

(* 2) The following shows how to read "Category."

(1)

Category	Particulars
M	Must
C	Conditional field
F	Musts after complementary
X	No entry is available.
-	Ignore the entry.

(2) "Category" level

(Ex.)

Field Name	Category	
Field A	C	
Field B		M

Lower level fields are under the category of upper level fields.

* Field A is a conditional field, which is sometimes but not always entered.

Field B is compulsory at a level lower than Field A. If Field A is entered, Field B must be entered.

(* 3) Operation Codes are in the Advance Filing Rules web site (<http://www.naccscenter.com/afr/>).