

Procedure Name (Procedure Code)			Loading Description Notification (LDR)																												
Item No.	Column	Field name	ID	Attribute	Length	Repeat 1	Repeat 2	Condition												Code	Input Condition/Format										
								Notification				Correction				Cancellation															
1		Input Common Field		an	398			M				M				M															
2		Function Type Code	MDC	an	1			M				M				M															9: Notification 5: Correction 1: Cancellation
3		Loading Vessel Code	LVC	an	9			M				M				M					Call sign										
4		Loading Vessel Name	SPN	an	35			C				C				C															
5		Port of Loading Code	LOC	an	5			M				M				M					UN/LOCODE										
6		Voyage Number	KON	an	10			C				C				C															
7		Booking Number	BON	an	16			C				C				C															When no Export Control Number is entered, enter Booking Number is mandatory.
8		Booking Number Suffix	BNE	an	2			C				C				C															
9		Export Control Number	CNO	an	35			C				C				C															When no Booking Number is entered, enter the Export Control Number.
10		Notification Forwarding Party Code	NOC	an	5			M				M				M					User Code										
11		Reference Number for Internal Use	OFN	an	20			C				C				C															Enter [Reference Number for Internal Use] registered by ACL procedure and other procedures.
12		B/L Number	BLN	an	35			C				C				-															When no S/O Number is entered, enter B/L Number is mandatory.
13		Estimated Date of B/L Issuance	BLD	n	8			C				C				-															
14		Estimated Time of B/L Issuance	BLT	n	4				M				M			-															
15		S/O Number	SON	an	35			C				C				-															When no B/L Number is entered, enter S/O Number is mandatory.
16		Total Prepaid Freight Currency Code	MU_	an	3	5		C				C				-					Currency Code (ISO4217, alphabet)										
17		Total Prepaid Freight (Foreign Currency)	MG_	n	10	*			M				M			-															(1) Integer: 7 digits / Decimal: 2 digits (2) A negative value can be entered. (Up to 10 digits can be entered including the minus sign and the decimal point.)
18		Exchange Rate	MO_	n	12	*			M				M			-															Integer: 7 digits / Decimal: 4 digits
19		Total Prepaid Freight (yen)	MGE	n	10							C				C															(1) Enter [Total Prepaid Freight (yen)] if [Total Prepaid Freight Currency Code] is entered. (2) A negative value can be entered. (Up to 10 digits can be entered including the minus sign.)
20		Total Collect Freight Currency Code	AU_	an	3	5		C				C				-					Currency Code (ISO4217, alphabet)										
21		Total Collect Freight (Foreign Currency)	AF_	n	10	*			M				M			-															(1) Integer: 7 digits / Decimal: 2 digits (2) A negative value can be entered. (Up to 10 digits can be entered including the minus sign and the decimal point.)
22		Remark	KIJ	j	140			C				C				-															
23	20	Fee Name	R01	an	20			C				C				-															
24	*	Quantity Applied for Freight Calculation	U01	n	10			C				C				-															Integer: 6 digits / Decimal: 3 digits
25	*	Quantity Unit Applied for Freight Calculation	K01	an	10				M				M			-															
26	*	Freight Currency Code	S01	an	3			C				C				-					Currency Code (ISO4217, alphabet)										

Procedure Name (Procedure Code)			Loading Description Notification (LDR)																			
Item No.	Column	Field name	ID	Attribute	Length	Repeat 1	Repeat 2	Condition												Code	Input Condition/Format	
								Notification				Correction				Cancellation						
27	*	Unit Price Applied for Freight Calculation	T01	n	10				M				M			-						(1) Integer: 7 digits / Decimal: 2 digits (2) A negative value can be entered. (Up to 10 digits can be entered including the minus sign and the decimal point.)
28	*	Freight (Foreign Currency)	E01	n	10			C				C				-						(1) Integer: 7 digits / Decimal: 2 digits (2) A negative value can be entered. (Up to 10 digits can be entered including the minus sign and the decimal point.)
29	*	Freight Payment Code	C01	an	1			C				C				-				UN/EDIFACT code (4237)	P: Prepaid C: Collect	