

Procedure Name (Procedure Code)		Loading Description Notification (LDR)																		
Item No.	Column	Field name	ID	Attribute	length	Repeat 1	Repeat 2	Condition						Code	Input Condition/Format					
								Notification			Correction					Cancellation				
1		Input Common Field		an	398			M				M								
2		Function Type Code	MDC	an	1			M				M								9: Notification 5: Correction 1: Cancellation
3		Loading Vessel Code	LVC	an	9			M				M								Call sign
4		Loading Vessel Name	SPN	an	35			C				C								
5		Port of Loading Code	LOC	an	5			M				M								UN/LOCODE
6		Voyage Number	KON	an	10			C				C								
7		Booking Number	BON	an	16			C				C								When no Export Control Number is entered, enter the Booking Number.
8		Booking Number Suffix	BNE	an	2			C				C								
9		Export Control Number	CNO	an	35			C				C								When no Booking Number is entered, enter the Export Control Number.
10		Notification Forwarding Party Code	NOC	an	5			M				M								User Code
11		Reference Number for Internal Use	OFN	an	20			C				C								Enter [Reference Number for Internal Use] registered by ACL procedure and other procedures.
12		B/L Number	BLN	an	35			C				C								When no S/O Number is entered, enter B/L Number is mandatory.
13		Estimated Date of B/L Issuance	BLD	n	8			C				C								
14		Estimated Time of B/L Issuance	BLT	n	4			M				M								
15		S/O Number	SON	an	35			C				C								When no B/L Number is entered, enter of S/O Number.
16		Total Prepaid Freight Currency Code	MU_	an	3	5		C				C								Currency Code (ISO4217, alphabet)
17		Total Prepaid Freight (Foreign Currency)	MG_	n	10	*		M				M								(1) Integer: 7 digits / Decimal: 2 digits (2) A negative value can be entered. (Up to 10 digits can be entered including the minus sign and the decimal point.)
18		Exchange Rate	MO_	n	12	*		M				M								Integer: 7 digits / Decimal: 4 digits
19		Total Prepaid Freight (yen)	MGE	n	10			C				C								(1) Enter [Total Prepaid Freight (yen)] if [Total Prepaid Freight Currency Code] is entered. (2) A negative value can be entered. (Up to 10 digits can be entered including the minus sign.)
20		Total Collect Freight Currency Code	AU_	an	3	5		C				C								Currency Code (ISO4217, alphabet)
21		Total Collect Freight (Foreign Currency)	AF_	n	10	*		M				M								(1) Integer: 7 digits / Decimal: 2 digits (2) A negative value can be entered. (Up to 10 digits can be entered including the minus sign and the decimal point.)
22		Remark	KIJ	j	140			C				C								
23	20	Fee Name	R01	an	20			C				C								
24	*	Quantity Applied for Freight Calculation	U01	n	10			C				C								Integer: 6 digits / Decimal: 3 digits
25	*	Quantity Unit Applied for Freight Calculation	K01	an	10			M				M								
26	*	Freight Currency Code	S01	an	3			C				C								Currency Code (ISO4217, alphabet)
27	*	Unit Price Applied for Freight Calculation	T01	n	10			M				M								(1) Integer: 7 digits / Decimal: 2 digits (2) A negative value can be entered. (Up to 10 digits can be entered including the minus sign and the decimal point.)

Procedure Name (Procedure Code)		Loading Description Notification (LDR)																	
Item No.	Column	Field name	ID	Attribute	length	Repeat 1	Repeat 2	Condition						Code	Input Condition/Format				
								Notification			Correction					Cancellation			
28	*	Freight (Foreign Currency)	E01	n	10			C				C			-				(1) Integer: 7 digits / Decimal: 2 digits (2) A negative value can be entered. (Up to 10 digits can be entered including the minus sign and the decimal point.)
29	*	Freight Payment Code	C01	an	1			C				C			-				UN/EDIFACT code (4237) P: Prepaid C: Collect