1 1 2 3 4 5 6 6 7	Field name Input Common Field Function Type Code Vessel Code Voyage Number Carrier Code Port of Discharge Code Estimated Date of Arrival	ID KND SEN VOY SCA	an an an	9	Repeat 1	M C M		С	ond	ition				Code	Input Condition/Format 9: Registration
3 4 5 6	Input Common Field Function Type Code Vessel Code Voyage Number Carrier Code Port of Discharge Code	KND SEN VOY SCA	an an an	398 1 9	Repeat	C M								Code	·
3 3 4 5 6	Function Type Code Vessel Code Voyage Number Carrier Code Port of Discharge Code	SEN VOY SCA	an an an	9		C M									9: Registration
3 4 5 6	Vessel Code Voyage Number Carrier Code Port of Discharge Code	SEN VOY SCA	an an	9		М									9: Registration
5	Voyage Number Carrier Code Port of Discharge Code	VOY	an	10						_					NACCS package software users do not have to enter the code.
5	Carrier Code Port of Discharge Code	SCA	an			М								Call sign	
6	Port of Discharge Code			4											
		DPR	an			 М									Enter the NACCS Carrier Code.
7	Estimated Date of Arrival			5		М								UN/LOCODE	(1) Enter [Port of Discharge Code] (Temporary Landing Port for temporary landing).(2) The code must be registered as for foreign vessel.
		IDT	n	8		М									
8	Estimated Time of Arrival	IHM	n	4		М									
9	Discharge Start Date	SDT	n	8		М									
10	Discharge Start Time	SHM	n	4		С									(1) Enter [Discharge Start Time] if [Discharge Finish Time] is entered. (2) [Discharge Start Time] cannot be entered if [Discharge Finish Time] is not entered.
11	Discharge Finish Date	EDT	n	8		М									Discharge Start Date shall be the ≦ Discharge Finish Date
12	Discharge Finish Time	ЕНМ	n	4		С									 (1) Enter [Discharge Finish Time] if [Discharge Start Time] is entered. (2) [Discharge Finish Time] cannot be entered if [Discharge Start Time] is not entered. (3) If [Discharge Start Date = Discharge Finish Date], then [Discharge Start Time shall be the ≦ Discharge Finish Time]
13	Notification Forwarding Party Code	CA_	an	5	2	С								User Code	(1) Enter the User Code of the implementer to send [Application for Cargo Discharge Permission (Copy)] and [Discharge permit notice] to other users. (2) The code must be entered sequentially from the first column. (3) The implementer's User Code cannot be entered. (4) The same User Code cannot be entered twice.
14	Process Identifier	TES	an	1		С									If the B/L Number is entered in the columns, one of more columns should have a space. Space: For application X: Not for application
15 *	B/L Number	BLN	an	35		М						+	+		-